




AD-A286 919



**Defense Special Weapons Agency
Alexandria, VA 22310-3398**



DNA-TR-96-99

Users Manual for Nevada Test Site Database (NTS-DB) Software

**Howard G. White
Brian H. Green
USAE Waterways Experiment Station
3909 Halls Ferry Road
Vicksburg, MS 39180-6199**

April 1997

Technical Report

DTIC QUALITY ASSURED

MIPRs HD1102-4-124A01 and HD1102-6-B4502

Approved for public release
distribution is unlimited

A-1 97-00613

DESTRUCTION NOTICE:

Destroy this report when it is no longer needed.
Do not return to sender.

PLEASE NOTIFY THE DEFENSE SPECIAL WEAPONS
AGENCY, ATTN: CSTI, 6801 TELEGRAPH ROAD,
ALEXANDRIA, VA 22310-3398, IF YOUR ADDRESS IS
INCORRECT, IF YOU WISH IT DELETED FROM THE
DISTRIBUTION LIST, OR IF THE ADDRESSEE IS NO
LONGER EMPLOYED BY YOUR ORGANIZATION.



DISTRIBUTION LIST UPDATE

This mailer is provided to enable DSWA to maintain current distribution lists for reports. (We would appreciate your providing the requested information.)

- ☐ Add the individual listed to your distribution list
- ☐ Delete the cited organization/individual.
- ☐ Change of address.

NOTE:

Please return the mailing label from the document so that any additions, changes, corrections or deletions can be made easily. For distribution cancellation or more information call DSWA/IMAS (703) 325-1036.

NAME: _____

ORGANIZATION: _____

OLD ADDRESS

CURRENT ADDRESS

TELEPHONE NUMBER: () _____

DSWA PUBLICATION NUMBER/TITLE

CHANGES/DELETIONS/ADDITIONS, etc.)
(Attach Sheet if more Space is Required)

DSWA OR OTHER GOVERNMENT CONTRACT NUMBER: _____

CERTIFICATION OF NEED-TO-KNOW BY GOVERNMENT SPONSOR (if other than DSWA):

SPONSORING ORGANIZATION _____

CONTRACTING OFFICER OR REPRESENTATIVE _____

SIGNATURE: _____

CUT HERE AND RETURN



DEFENSE SPECIAL WEAPONS AGENCY
ATTN: IMAS
6801 TELEGRAPH ROAD
ALEXANDRIA, VA 22310-3398

DEFENSE SPECIAL WEAPONS AGENCY
ATTN: IMAS
6801 TELEGRAPH ROAD
ALEXANDRIA, VA 22310-3398

REPRODUCTION QUALITY NOTICE

This document is the best quality available. The copy furnished to DTIC contained pages that may have the following quality problems:

- **Pages smaller or larger than normal.**
- **Pages with background color or light colored printing.**
- **Pages with small type or poor printing; and or**
- **Pages with continuous tone material or color photographs.**

Due to various output media available these conditions may or may not cause poor legibility in the microfiche or hardcopy output you receive.

☐ **If this block is checked, the copy furnished to DTIC contained pages with color printing, that when reproduced in Black and White, may change detail of the original copy.**

REPORT DOCUMENTATION PAGE			Form Approved OMB No. 0704-0188	
<small>Public Reporting Burden: This collection of information is estimated to average 1 hour per response, including the time for reviewing instructions, searching existing data sources, gathering and maintaining the data needed, and completing and reviewing the collection of information. Send comments regarding this burden estimate or any other aspect of this collection of information, including suggestions for reducing the burden, to Washington Headquarters Services, Directorate for Information Operations and Reports, 1215 Jefferson Davis Highway, Suite 1204, Arlington, VA 22202-4302, and to the Office of Management and Budget, Paperwork Reduction Project (0704-0188), Washington, DC 20503.</small>				
1 AGENCY USE ONLY (Leave blank)	2 REPORT DATE 970401	3 REPORT TYPE AND DATES COVERED Technical 940517 - 960930		
4 TITLE AND SUBTITLE Users Manual for Nevada Test Site Database (NTS-DB) Software		5 FUNDING NUMBERS MIFR - HD1102-4-124A01 HD1102-6-B4502		
6 AUTHOR(S) Howard G. White and Brian H. Green				
7 PERFORMING ORGANIZATION NAME(S) AND ADDRESS(ES) USAF Waterways Experiment Station 3909 Halls Ferry Road Vicksburg, MS 39180-6199		8 PERFORMING ORGANIZATION REPORT NUMBER		
9 SPONSORING/MONITORING AGENCY NAME(S) AND ADDRESS(ES) Field Command Defense Special Weapons Agency Test Directorate 1680 Texas Street SE Kirtland AFB, NM 87117-5669		10 SPONSORING/MONITORING AGENCY REPORT NUMBER DNA-TR-96-99		
11 SUPPLEMENTARY NOTES				
12a DISTRIBUTION/AVAILABILITY STATEMENT Approved for public release; distribution is unlimited.		12b DISTRIBUTION CODE		
13. ABSTRACT (Maximum 200 words) <p>The U.S. Army Engineer Waterways Experiment Station was actively involved in the development, testing, and fielding of a wide variety of grout and concrete mixtures in support of underground nuclear test programs at the Nevada Test Site. Detailed information on mixture designs, laboratory data such as unconfined compressive strength, sonic velocity, density, and modulus, and similar results for actual as-placed mixtures have been archived in a computerized database. There are 264 mixture designs included in the database that were fielded at 2,132 locations on 48 underground nuclear tests between February, 1970, and September, 1992. There are over 67,000 data entries in the database. The software, entitled NTS-DB, used to query this database is a user-friendly Windows-format code that provides almost unlimited flexibility in specifying a query criterion.</p> <p>Also provided with the NTS-DB software and database is the Windows Help-like Grout Users Manual. The manual provides guidance to those who are not knowledgeable in the area of grout mixture proportioning, materials, mixing, and placing.</p>				
14 SUBJECT TERMS Grout Groutcrete Concrete Nevada Test Site Database Grout Users Manual		15 NUMBER OF PAGES 52		
		16 PRICE CODE		
17 SECURITY CLASSIFICATION OF REPORT UNCLASSIFIED	18 SECURITY CLASSIFICATION OF THIS PAGE UNCLASSIFIED	19 SECURITY CLASSIFICATION OF ABSTRACT UNCLASSIFIED	20 LIMITATION OF ABSTRACT SAR	

NSN 7540-280-5500

Standard Form 298 (Rev 2-89)
Prescribed by ANSI Z39-18
298-102

UNCLASSIFIED
NOT BE CLASSIFIED IN THIS PAGE

CLASSIFIED BY:

N/A since Unclassified

DECLASSIFY ON:

N/A since Unclassified.

SECURITY CLASSIFICATION OF THIS PAGE
UNCLASSIFIED

PREFACE

The work described in this user's manual was sponsored by the Field Command, Defense Special Weapons Agency (DSWA). Funding was provided under MIPRs HD1102-4-I24A01, dated 17 May, 1994, and HD1102-6-B45H02, dated 5 December, 1995. Dr. George Baladi was the DSWA Project Manager.

This study was conducted by the Geomechanics and Explosion Effects Division (GEED), Structures Laboratory (SL), U.S. Army Engineer Waterways Experiment Station (WES), Vicksburg, MS. Dr. Howard G. White, GEED, was the principal investigator. Numerous persons assisted in various aspects of the software development. These included Messrs. John Boa and Brian Green, Concrete and Materials Division, WES, who assembled data and provided technical assistance, respectively, and Mr. Jonathan Ashley, a contractor to the GEED, who populated the database. During this investigation, Dr. Jimmy P. Balsara was Chief, GEED, and Mr. Bryant Mather was Director, SL.

At the time of publication of this report, Director of WES was Dr. Robert W. Whalin. Commander was COL Bruce K. Howard, EN.

The NTS DB software and accompanying database may be obtained by sending a written request to Director, USAE Waterways Experiment Station, ATTN: Engineering Computer Programs Library (CEWES-IM-DS), 3909 Halls Ferry Road, Vicksburg, MS 39180-6199.

CONVERSION TABLE

Conversion factors for U.S. Customary to metric (SI) units of measurement.

MULTIPLY BY TO GET
TO GET BY DIVIDE

angstrom	1.000 000 X E -10	meters (m)
atmosphere (normal)	1.013 25 X E +2	kilo pascal (kPa)
bar	1.000 000 X E +2	kilo pascal (kPa)
barn	1.000 000 X E -28	meter ² (m ²)
British thermal unit (thermochemical)	1.054 350 X E +3	joule (J)
calorie (thermochemical)	4.184 000	joule (J)
cal (thermochemical/cm ²)	4.184 000 X E -2	mega joule/m ² (MJ/m ²)
curie	3.700 000 X E +1	giga becquerel (GBq)
degree (angle)	1.745 329 X E -2	radian (rad)
degree Fahrenheit	$t_F = (t_C + 459.67)/1.8$	degree kelvin (K)
electron volt	1.602 19 X E -19	joule (J)
erg	1.000 000 X E -7	joule (J)
erg/second	1.000 000 X E -7	watt (W)
foot	3.048 000 X E -1	meter (m)
foot-pound-force	1.355 818	joule (J)
gallon (U.S. liquid)	3.785 412 X E -3	meter ³ (m ³)
inch	2.540 000 X E -2	meter (m)
jerk	1.000 000 X E +9	joule (J)
joule/kilogram (J/kg) radiation dose absorbed	1.000 000	Gray (Gy)
kiloton	4.183	terajoules
kip (1000 lbf)	4.448 222 X E +3	newton (N)
kip/inch ² (ksi)	6.894 757 X E +3	kilo pascal (kPa)
kN	1.000 000 X E +2	newton-second/m ² (N-s/m ²)
micron	1.000 000 X E -6	meter (m)
mil	2.540 000 X E -5	meter (m)
mile (international)	1.609 344 X E +3	meter (m)
ounce	2.834 952 X E -2	kilogram (kg)
pound-force (lbf avoirdupois)	4.448 222	newton (N)
pound-force inch	1.129 848 X E -1	newton-meter (N-m)
pound-force/inch	1.751 268 X E +2	newton/meter (N/m)
pound-force/foot ²	4.788 026 X E -2	kilo pascal (kPa)
pound-force/inch ² (psi)	6.894 757	kilo pascal (kPa)
pound-mass (lbf avoirdupois)	4.535 924 X E -1	kilogram (kg)
pound-mass-foot ² (moment of inertia)	4.214 011 X E -2	kilogram-meter ² (kg-m ²)
pound-mass/foot ³	1.601 846 X E +1	kilogram/meter ³ (kg/m ³)
rad (radiation dose absorbed)	1.000 000 X E -2	Gray (Gy)
roentgen	2.579 780 X E -4	coulomb/kilogram (C/kg)
shake	1.000 000 X E -8	second (s)
slug	1.459 390 X E +1	kilogram (kg)
torr (mm Hg, 0° C)	1.333 22 X E -1	kilo pascal (kPa)

*The becquerel (Bq) is the SI unit of radioactivity; 1 Bq = 1 event/s.
**The Gray (Gy) is the SI unit of absorbed radiation.

TABLE OF CONTENTS

Section	Page
PREFACE	iii
CONVERSION TABLE	iv
FIGURES	vi
1 INTRODUCTION	1
1.1 INTRODUCTION.....	1
1.2 SCOPE	2
2 INSTALLING NTS-DB	3
2.1 SYSTEM REQUIREMENTS	3
2.2 INSTALLATION	3
2.3 CHANGES TO YOUR SYSTEM	3
2.4 GROUT USER'S MANUAL	4
2.5 TECHNICAL SUPPORT, BUG REPORTS, AND COMMENTS.....	4
3 USER'S MANUAL FOR NTS-DB.....	5
3.1 GETTING STARTED	5
3.2 BEGINNING A QUERY	5
3.2.1 To Query on a Mixture Name or Test Name	5
3.2.2 To Query on Properties and/or Components	6
3.3 COMMON FEATURES OF THE PROPERTY/COMPONENT FORM AND NAME FORM.....	7
3.3.1 List Boxes	7
3.3.1.1 Property/Component Form.....	7
3.3.1.2 Name Form	7
3.3.2 Command Buttons	7
3.4 GENERAL INFO FOR DISPLAYING PROPERTY DATA.....	8
3.4.1 Field Data Plotting Options Form.....	8
3.4.2 Field Data Form and Laboratory Data Form	9
4 CONCLUSIONS AND RECOMMENDATIONS.....	21
4.1 CONCLUSIONS.....	21
4.2 RECOMMENDATIONS.....	21
Appendix	
GLOSSARY	A-1

FIGURES

Figure	Page
3-1 Organization of NTS-DB	12
3-2 The Main Form is the initial form loaded by NTS-DB.....	12
3-3 The About NTS DB Form is accessed by clicking the NTS-DB icon, i.e., the concrete truck, on the Main Form.....	13
3-4 The Name Form is displayed in response to a query on a Mixture Name or a Test Name.....	14
3-5 The Main Form, Property/Component Query is used to develop a query criterion by allowing the user to specify bounds on properties and/or to select components to be included in the query.....	15
3-6 The Property/Component Form is displayed in response to a query on properties and/or components.....	16
3-7 The list of materials (or components) used in the mixture is displayed after clicking the Materials List command button on the Property/Component Form or Name Form	16
3-8 The Mixture and Plastic Data Form is used to display various mixture data determined in the laboratory.....	17
3-9 The Field Data Plotting Options Form allows the user to choose which field data to view. This form is also used to display field notes pertinent to a given placement of the mixture on a field test	18
3-10 The Field Data Form is used to the display property data selected by the user from the Field Data Plotting Options Form.....	19
3-11 The Laboratory Data Form is used to display property data determined in the laboratory	20

SECTION 1

INTRODUCTION

1.1 INTRODUCTION.

The Concrete and Materials Division of the U.S. Army Engineer Waterways Experiment Station developed, tested, and fielded a wide variety of concrete, grout, and groutcrete mixtures in support of underground nuclear weapons effects testing programs at the Nevada Test Site. Detailed information on mixture designs, laboratory data such as unconfined compressive strength, sonic velocity, density, and modulus, and similar results for actual as-placed mixtures have been archived in a user-friendly Windows-based computerized database.

The database file may be queried using the NTS-DB software. This software has been organized with two primary users in mind:

Mixture designers: someone developing a mixture that has a certain requirement. For example, the mixture must attain 3000-4000 psi¹ (20.7-27.6 MPa) at 14 days and must contain steel fibers. The user would specify a Property/Component query (see Chapter 3).

NTS experimenters: someone who would like information about a specific mixture or test. This user must know the name of the mixture or test, and would execute a Name query (see Chapter 3).

The available data are divided into two major categories:

Laboratory Data: data obtained from specimens prepared in the lab. These data are unique for a given mixture, i.e., no matter how many different field tests used the mixture, only one set of laboratory data exists.

Field Data: data obtained from specimens prepared in the field. A mixture may have been used on several tests. Data may be viewed for all tests using the mixture, for a single test, or for a single location on a single test.

There are 264 mixture designs included in the NTS-DB database that were fielded at 2,132 locations on 48 underground nuclear tests between February, 1970, and September, 1992. There are over 67,000 data entries in the database, including:

- 140 grouts, 48 concretes, 69 groutcretes, 7 unclassified materials.

¹ The English system of units is used in the NTS-DB software. This system was chosen at the sponsor's (DSWA) request and because the data were originally recorded in the English system. SI units are provided in this manual for convenience.

-
- unconfined compressive strength: between 25 and 15,335 psi.
 - sonic velocities between 1,220 and 16,330 ft/sec.
 - densities between 54 and 130.2 lb/cu ft.

1.2 SCOPE.

This report documents the NTS-DB software and its use. Chapter 2 presents installation information and describes changes made to your computer system upon installation. Chapter 3 documents the NTS-DB software by providing general information on how to initiate a query and view the results. Chapter 4 states conclusions and recommendations.

SECTION 2

INSTALLING NTS-DB

2.1 SYSTEM REQUIREMENTS.

The minimum recommended system requirements for using NTS-DB are:

Computer: A 486 class processor. 8 MB RAM.

Disk Space: 10 Mbytes free disk space.

Monitor: VGA (640 x 480) graphics adapter.

Mouse: because some NTS-DB features are not accessible from the keyboard, a mouse is recommended.

2.2 INSTALLATION.

NTS-DB files are in compressed format on the distribution disks, therefore you must use the SETUP file included on Disk 1. To install NTS-DB on your hard disk,

1. Insert Disk 1 into drive A (or drive F).
2. Choose RUN from the FILE menu in the Windows Program Manager.
3. Type *a:setup* (or *b:setup*), then choose OK.
4. Accept the default, or type the location for SETUP to install NTS-DB, then choose OK.

2.3 CHANGES TO YOUR SYSTEM.

The files listed below, which require approximately 5.5 Mbytes disk space, are copied to your hard drive to the \WINDOWS\SYSTEM directory during the installation procedure. Many of these files may already reside on your hard drive. In these cases, the files are not recopied to your system.

The following files are copied to the \WINDOWS\SYSTEM directory:

CHART2FX.VBX	DOA2516.DLL	OLE2CONV.DLL	THREED16.OCX
COMDLG16.OCX	MSAJT200.DLL	OLE2DISP.DLL	TRUEGRID.VBX
COMPOBJ.DLL	MSJETERR.DLL	OLE2NLS.DLL	TYPELIB.DLL
CSCMD.VBX	MSJETINT.DLL	OLE2PROX.DLL	VAEN21.OLB
CSCOMBO.VBX	OC25.DLL	SCP.DLL	VB4C016.DLL
CSTEXT.VBX	OLE2.DLL	STDOLE.TLB	VBAJET.DLL
CTL3DV2.DLL	OLE2.REG	STORAGE.DLL	VBDDB16.DLL

The following files are copied to the NTSDB directory. These files require approximately 4.3 Mbytes disk space:

Filename	Function
DATAPCP.MDB	Database of mixtures
NTSDB.EXE	NTSDB executable file
NTSDB.HLP	NTSDB online help file
GUM.HLP	Grout User's Manual

The file DATAPCP.MDB is in Microsoft Access format. The contents of this file cannot be changed with the NTS-DB software. However, it is possible to alter the data contained in the DATAPCP.MDB database using other database software, e.g., Microsoft Access. It is recommended that the data in DATAPCP.MDB *not* be altered. The USAE Waterways Experiment Station will maintain the database and provide periodic updates as additional data become available.

2.4 GROUT USER'S MANUAL.

The file GUM.HLP is a Windows Help-like document and is *not* required to run NTS-DB. The main purpose of the Grout User's Manual is to provide guidance to those who are not knowledgeable in the area of grout mixture proportioning, materials, mixing, and placing. It is intended to provide very basic, elementary information and to impart a working knowledge of what is important to insure a successful grout placement near instruments used to monitor explosive events.

The Grout User's Manual discusses the proportioning or designing of a mixture (how to make it), actual mixing (how to mix it) and placement (how to get it in place). These three phases are the backbone of a successful grouting operation. The information presented is neither limiting nor all inclusive but is intended primarily for familiarization. To access the Grout User's Manual, simply double-click the GUM icon in the NTS-DB program group.

2.5 TECHNICAL SUPPORT, BUG REPORTS, AND COMMENTS.

Every effort has been made to rid the NTS-DB software of bugs. Before reporting any suspected bugs, it is important that you be able to reproduce the circumstances that led to an error. Please include the full version number of the code in any correspondence. Attempt to recreate the error by performing the same functions that led to it previously. A full description of the circumstances leading to the error should be addressed to: USAE Waterways Experiment Station, ATTN: CEWES-SD-R (H. G. White), 3909 Halls Ferry Road, Vicksburg, MS 39180-6199. Technical questions about mixture design or the data presented by NTS-DB should be addressed to USAE Waterways Experiment Station, ATTN: CEWES-SC-CA (B. H. Green), 3909 Halls Ferry Road, Vicksburg, MS 39180-6199

SECTION 3

USER'S MANUAL FOR NTS-DB

3.1 GETTING STARTED.

To launch the NTS-DB software, open the NTS-DB Program Group within Windows and simply double-click the NTS-DB icon (a concrete truck). An alternative method of launching the software would be to:

1. Choose RUN from the FILE menu in the Windows Program Manager.
2. Type *path:\ntsdb* where *path*, is the location of the NTS-DB software on your hard drive, e.g., c:\ntsdb.
3. Click OK.

The structure of the NTS-DB program is shown in Figure 3-1. The program begins by loading the Main Form (see Figure 3-2). The type of query is specified on the Main Form, i.e., either a Property/Component query or a Name query. Also, the About NTS-DB Form (see Figure 3-3) may be accessed by clicking the NTS-DB icon on the Main Form. *Hint:* the animation of the concrete truck may be stopped and started by right-clicking the icon.

3.2 BEGINNING A QUERY.

To begin a query:

1. Start on the Main Form (Figure 3-2).
2. Choose to **Query a Property and/or Component²**, or **Query a Mixture Name or Test Name**.
3. The query process may be initialized at any time by clicking **Cancel**.

3.2.1 To Query on a Mixture Name or Test Name.

Clicking **Query a Mixture Name or Test Name** on the Main Form (Figure 3-2) immediately displays the Name Form (see Figure 3-4). Select a mixture name from the **Mixture Name List Box** or a test name from the **Test Name List Box**.

² Buttons/boxes available on various NTS-DB forms are shown in **bold face type** in this manual. Definitions of the buttons/boxes are contained in the Glossary at the end of this manual.




Figure 3-1. Organization of NTS-DB




Figure 3-2. The Main Form is the initial form loaded by NTS-DB.




Figure 3-3. The About NTS-DB Form is accessed by clicking the NTS-DB icon, i.e., the concrete truck, on the Main Form.




Figure 3-4. The Name Form is displayed in response to a query on a Mixture Name or a Test Name.

3.2.2 To Query on Properties and/or Components

Clicking **Query a Property and/or Component** on the Main Form (Figure 3-2) changes the display of the Main Form so that a query may be initiated. Presented in Figure 3-5 is an example of the Main Form for a query on Properties and/or Components.

Several properties of a mixture may be queried. These include Strength, Velocity, Density, Static Modulus, Dynamic Modulus, Expansion, Mixture Class, and Slump (laboratory data only). Also, the user may choose to search either field data or laboratory data. Refer to the Glossary at the end of this manual for definitions of each of these terms.

The components used in the various mixtures contained in the database have been grouped into six categories. These include Fine Aggregates, Coarse Aggregates, Cementitious Materials, Chemical Admixtures, Mineral Admixtures, and Others. Any one component from each category may be included in a query.

To specify a query criterion:

1. If querying on properties, choose to query either **Field Data** or **Laboratory Data**. If laboratory data are chosen, Slump may be included in the query. The default is field data.
2. Choose any combination of properties on which to query by entering lower and/or upper bounds for the property. You may select suggested bounds by clicking the arrow adjacent to the lower and upper bound list boxes for each property and then clicking the desired value. A more specific bound may be entered by clicking in the appropriate list box and simply typing the value. Note: Age may be selected only in combination with another property.
3. If querying on components, the choices for a category are shown by clicking the arrow adjacent to the associated list box. Then click the component to be queried. To clear a component from a query, click the blank line at the top of the list of choices in the appropriate list box. All categories may be queried; however, only one component per category may be selected.
4. Click **Continue** to proceed with the query. If no mixtures meet the specified criterion, NTS-DB will display a message box indicating a null search, otherwise the Property/ Component Form will be displayed.




Figure 3-5. The Main Form, Property/Component Query is used to develop a query criterion by allowing the user to specify bounds on properties and/or to select components to be included in the query.

3.3 COMMON FEATURES OF THE PROPERTY/COMPONENT FORM AND NAME FORM.

The Property/Component Form (see Figure 3-6) and Name Form (see Figure 3-4) have similar formats. At the top of each form are list boxes that are used to display mixture names and test names. Along the left edge of the form are command buttons that allow the user to view information about the mixture selected or to begin a new query. At the bottom of the form are command buttons that invoke NTS-DB online help or return the user to the Main Form. The operation of NTS-DB in response to user actions on these forms is described below.

3.3.1 List Boxes.

3.3.1.1 Property/Component Form. When the user specifies a query on a Property and/or Component on the Main Form and clicks **Continue**, NTS-DB searches the database to find all mixtures that meet the specified criterion. If no mixtures meet the criterion, NTS-DB will display a message box indicating a null search, otherwise the Property/Component Form will be displayed. The results of the query are listed in the **Mixture Name List Box** (see the top of Figure 3-6). Click the list box to display the mixture names. Once a mixture is selected, NTS-DB searches the database to find all tests which used the mixture. The results of the search are displayed in the **Test Name List Box**.

3.3.1.2 Name Form. If the user specifies a query on a Mixture Name or Test Name on the Main Form, NTS-DB immediately displays the Name Form. NTS-DB searches the database to find all mixture names and test names and displays the results in the **Mixture Name List Box** and **Test Name List Box**, respectively. These list boxes are shown at the top of Figure 3-4.

The user may select either a mixture name or test name from one of the list boxes. If the user selects a mixture name, NTS-DB searches the database for all tests which used the mixture. Click on the **Test Name List Box** to see the results of the search. If the user selects a test name, NTS-DB searches the database for all mixtures used on the test. Click on the **Mixture Name List Box** to see the results of the search.

Each time the mixture name or test name is changed in one of the list boxes, NTS-DB updates the other list box to reflect the results of the search. To initialize the query, the user may select the first item in either of the list boxes, "Initialize Lists", or click **Initialize Query Lists** (described below).

3.3.2 Command Buttons.

Several command buttons are included on the Property/Component Form and Name Form (see Figures 3-6 and 3-4, respectively). The operation of NTS-DB in response to user actions is described below.

Button	Action
Materials List	View the list of materials used to prepare the mixture (see Figure 3-7). Two additional command buttons, Print and Close , are displayed with the materials list.
Print	Print a hard-copy of the materials list. Available after clicking Materials List .
Close	Close the materials list display. Available after clicking Materials List .
Criteria/Notes	View the original criteria for the mixture (if specified) and any notes recorded.
Mixture and Plastic Data	Display the Mixture and Plastic Data Form (see Figure 3-8).
Lab Test Data	Display the Laboratory Data Form. If this button is shaded then no data are available to plot.
Field Test Data	Display the Field Data Plotting Options Form. If this button is shaded then no data are available to plot.
Query Different Property/Comp	Available only on the Property/ Component Form, click this button to return to the Main Form, where the query may be modified (see Figure 3-6).
Initialize Query Lists	Available only on the Name Form, click this button to list all mixture names and test names in the list boxes (see Figure 3-4).
Help	Invoke NTS-DB online help.
Main	Return to the Main Form.

3.4 GENERAL INFO FOR DISPLAYING PROPERTY DATA

Property Data is displayed using the Field Data Form and the Laboratory Data Form. Prior to displaying the Field Data Form, the Field Data Plotting Options Form is displayed, allowing the user to specify the data to be plotted.

Gross		104	
127.5	170.5		
6.6	6.8		
Wet Weight		Wet Weight	
1.45	0		
<div> <div>Encl. not Mailed</div> <div> <div>Encl. not Mailed</div> <div>Encl. not Mailed</div> </div> </div>		<div> <div>Encl. not Mailed</div> <div>Encl. not Mailed</div> </div>	
		0.7	
		Encl. not Mailed	

Figure 3-8. The Mixture and Plastic Data Form is used to display various mixture data determined in the laboratory.

3.4.1 Field Data Plotting Options Form.

The Field Data Plotting Options Form (see Figure 3-9) is displayed in response to the user clicking **Field Test Data** on either the Property/Component Form or Name Form. This form is displayed prior to the Field Data Form and allows the user to select which field data to plot. This form is also used to display information specific to a mixture placement at a given location on a field test.

The user has the following options:

Select a Field Test: This list box contains the names of all field tests which included the selected mixture. A single test may be selected from the list or the first entry in the list, "View data from all field tests", may be selected to view all the data from applicable field tests. If the mixture was used on only one field test then the test name is automatically placed in the list box.

Select a Location: Available if a single test is selected in the Select a Field Test List Box. Select the location on a field test to view. A single location may be selected from the list or the first entry in the list, "View data from all locations", may be selected to view all data from a single field test. If the mixture was placed at only one location for the selected test then the location name is automatically placed in the list box. After a field location is selected, the Date Cast, Temperature Change, and Notes for the location are presented (when available)

Select Data to View: The field test data is divided into two distinct categories, **Prior to Shot Day** and **Shot Day**. Property data determined prior to the date on which a field test was conducted has an associated Age, i.e., the age at which the specimen was tested is known. On the contrary, the age at Shot Day is unknown. Therefore, for a history of a property, choose to plot Prior to Shot Day, because Shot Day data can not be plotted versus time.

Several command buttons are included on the Field Data Plotting Options Form. The operation of NTS-DB in response to user actions is described below.

Button	Action
Continue	Display the Field Data Form.
Different Mixture	Return to the Property/Component or Name Form (depending on the type of query being performed).
Help	Invoke NTS-DB online help.
Main	Return to the Main Form.




Figure 3-9. The Field Data Plotting Options Form allows the user to choose which field data to view. This form is also used to display field notes pertinent to a given placement of the mixture on a field test

3.4.2 Field Data Form and Laboratory Data Form.

The Field Data Form (see Figure 3-10) and Laboratory Data Form (see Figure 3-11) have a similar format. Option buttons allow the user to choose the property to be plotted on both the x- and y-axes. Any two properties may be plotted against one another, with the following exceptions:

1. Age may not be plotted on the y-axis.
2. A property may not be plotted against itself.
3. If no data are available for a given property, the option button is disabled (appearing gray), preventing the user from selecting it.

The user may choose from the following properties (when available): strength, velocity, density, static modulus, dynamic modulus, expansion, and age (x-axis only). The default selections are Strength versus Age.

Several command buttons are included on the Field Data Form and Laboratory Data Form. The operation of NTS-DB in response to user actions is described below.

Button	Action
Plot Data	Display a scatter plot of the specified data.
Different Mixture	Return to the Property/Component or Name Form (depending on the type of query being performed).
Different Options	Available only on the Field Data Form. Click Different Options to return to the Field Data Plotting Options Form (described above).
Help	Invoke NTS-DB online help.
Main	Return to the Main Form.

Once the data are displayed, a button bar is presented that allows the user to alter the display and export the data and/or graph. Exporting options include:

1. Saving the data values to a file.
2. Copying the plot image to the clipboard.
3. Copying the data values to the clipboard.
4. Printing a hard copy of the plot image.

The appearance of the display may be altered to:

1. Switch between 2-D and 3-D views of the graph (limited usefulness).




Figure 3-10. The Field Data Form is used to the display property data selected by the user from the Field Data Plotting Options Form.

A high-contrast, black and white image of a Laboratory Data Form. The form is divided into several sections by horizontal and vertical lines. The top section contains a small rectangular box with text inside. The main body of the form is a large rectangular area with a grid-like pattern, possibly for recording data. The image is heavily degraded with noise and artifacts, making the text and details difficult to discern.

Figure 3-11. The Laboratory Data Form is used to display property data determined in the laboratory.

2. Rotate the 3-D image of the graph (3-D only, limited usefulness).
3. Spread the individual data series along the z-axis (3-D only, limited usefulness).
4. Zoom-in on an area of the plot. Note: the axes are not visible in the zoom mode.
5. Display a legend of the series names (Field Data only).
6. Display vertical grid lines.
7. Display horizontal grid lines.
8. Change the text displayed.
9. Change the font of the titles.
10. Change the colors and/or patterns of the display, view the y-values of the data.
11. Open a toolbox that allows the user many options for altering the display.

Hints:

1. Double-click on a data point to see its (x,y) data values and series name (Field Data only).
2. Experiment with the data display using the buttons presented on the button bar. The user cannot alter the data contained in the database. To restore the display defaults simply click **Different Mixture** or **Different Options** and then return once again to the Field Data Form or Laboratory Data Form.

SECTION 4

CONCLUSIONS AND RECOMMENDATIONS

4.1 CONCLUSIONS.

The U.S. Army Engineer Waterways Experiment Station was actively involved in the development, testing, and fielding of a wide variety of grout and concrete mixtures in support of underground nuclear weapons effects testing programs at the Nevada Test Site. Detailed information on mixture designs, laboratory data such as unconfined compressive strength, sonic velocity, density, and modulus, and similar results for actual as-placed mixtures have been archived in a computerized database. The software, entitled NTS-DB (Nevada Test Site - Database), used to query this database is a user-friendly Windows-format code that provides almost unlimited flexibility in specifying a query criterion.

Also provided with the NTS-DB software and database is the Windows Help-like Grout User's Manual. The manual provides guidance to those who are not knowledgeable in the area of grout mixture proportioning, materials, mixing, and placing. It presents very basic, elementary information in order to impart a working knowledge of what is important to insure a successful grout placement near instruments used to monitor explosive events.

4.2 RECOMMENDATIONS.

The expertise developed by WES over the many years of service at NTS has enabled WES to better serve other sponsors as well. The Generic Grout Families study, conducted for the Corps of Engineers, drew heavily upon the experience gained from WES's participation on the underground nuclear tests at NTS. The mixtures developed for use at NTS typically contain several exotic ingredients. Those special ingredients were used to meet a specific requirement for a particular placement of a given mixture. It was thought that mixtures based on generic/common ingredients would be useful as less complex points-of-departure for future mixtures. Under this study 13 families of grouts were identified. Each family was categorized based on the ingredients in the mixture, e.g., Family 1 is cement and water; Family 2 is cement, water, and bentonite; and Family 7 is cement, water, sand, and fly ash. The result of this study is a comprehensive matrix of mixtures that can be used by the layman mixture designer.

It is recommended that the Generic Grout Families database be coupled with the NTS-DB software. The inclusion of the database could be manifested in one of two ways. One method would be to create a stand-alone query code, similar to NTS-DB. The preferred method for including the additional data would be to modify the NTS-DB software by simply adding an option to query the generic families data. A form similar

to that available for a Property/Component query could be used to develop a criterion for querying the generic families database.

APPENDIX
GLOSSARY OF TERMS

Age

Time, in days, at which a specimen was tested.

Air Content

The volume of air voids in cement paste, exclusive of pore space in aggregate particles, expressed as a percentage of total volume of the mixture; determined according to ASTM C 231 or COE CRD C 41. Available for laboratory data only.

Presented on the Mixture and Plastic Data Form

Bleeding

The autogenous flow of mixing water within, or its emergence from a newly placed mixture; caused by the settlement of the solid materials within the mass; determined according to ASTM C 940 (grouts) or COE CHD C 613. Available for laboratory data only.

Presented on the Mixture and Plastic Data Form.

By Weight Of

A listing of the cementitious materials used to calculate the water/cement ratio. Available for laboratory data only.

Presented on the Mixture and Plastic Data Form.

Hint: Click the Materials List command button for a list of materials used in the mixture.

Cancel

Click **Cancel** to cancel the specified query.

Available on the Main Form.

Cementitious Factor

A measure of cementitious materials in the mixture, expressed as bags/cu yd. Available for laboratory data only.

Presented on the Mixture and Plastic Data Form.

Close

Click Close to close the Materials List display for a mixture.

Available on the Property/Component and Name Forms after the Materials List button is clicked.

Component

A material used in the design of a mixture.

Continue, Field Data Plotting Options Form

Click Continue to display the Field Data Form.

Continue, Main Form

Click Continue to execute the specified query.

Criteria/Notes

Click Criteria/Notes to view the original criteria for the mixture (if specified) and any notes recorded.

Available on the Property/Component and Name Forms.

Date Cast

The date the mixture was placed at a location on a field test.

Presented on the Field Data Plotting Options Form (when available) after selecting an item from the Select a Location List Box.

Density

Mass per unit volume of the mixture, expressed as lb/cu ft; determined according to ASTM C 642.

Different Mixture

Click Different Mixture to return to the Property/Component or Name Form (depending on the type of query being performed).

Different Options

Click Different Options to return to the Field Data Plotting Options Form.

Available on the Field Data Form.

Dynamic Modulus

The modulus of elasticity computed from the size, weight, shape, and fundamental frequency of vibration of a specimen, or from pulse velocity, according to ASTM C 215.

Exit

Click Exit to quit NTS-DB.

Available on the Main Form.

Expansion

Material property determined according to ASTM C 878 and C 490. Positive expansion indicates an increase in volume. Negative expansion indicates a decrease in volume, i.e., shrinkage.

Field Data

Data obtained from specimens prepared in the field (Nevada Test Site). A query of field data searches all the field data and returns mixtures which meet the specified criterion.

Field Test Data

Click Field Test Data to display the Field Data Plotting Options Form. This item is disabled if there are no data available to plot.

Available on the Property/Component and Name Forms.

Flow

A measure of the consistency of a grout in which a predetermined volume is permitted to escape through a precisely sized orifice, the time of efflux being used as the indication of consistency; determined according to ASTM C 939. Available for laboratory data only.

Presented on the Mixture and Plastic Data Form.

Groutcrete

A mixture that exhibits properties generally between those typical for grouts or concretes; similar to mortar.

Help

Click Help to invoke NTS-DB online help.

Initialize Query Lists

Click Initialize Query Lists to list all mixture names and test names in the list boxes.

Available on the Name Form.

Lab Test Data

Click Lab Test Data to display the Laboratory Data Form. This item is disabled if there are no data available to plot.

Available on the Property/Component and Name Forms.

Laboratory Data

Data obtained from specimens prepared in the laboratory. A query of laboratory data searches all the laboratory data and returns mixtures which meet the specified criterion.

The laboratory data for a given mixture is unique, i.e., only one set of laboratory data exists for the mixture, even though it may have been used on numerous tests. As a result the total amount of laboratory data available for query, while quite large, is considerably smaller than the set of field data.

Main

Click Main to return to the Main Form.

Materials List

Click Materials List to view a list of materials used to prepare the mixture.

Available on the Property/Component and Name Forms.

Mixture and Plastic Data

Click Mixture and Plastic Data to display the Mixture and Plastic Data Form.

Available on the Property/Component and Name Forms.

Mixture Class

Mixtures included in the database are placed into three general classes: Grout, Concrete, or Groutcrete.

Presented on the Mixture and Plastic Data Form.

Mixture Name

The name of a mixture.

The names, for the most part, were assigned by WES personnel. A loosely applied guide was followed in naming many (not all) of the mixtures. The first two initials generally refer to a Test Name, e.g. a mixture developed for the test Diamond Skulls might begin with DS. Other initials often refer to the type of mixture, e.g., a groutcrete (gc) or a high strength grout (hsg). Still other initials or numbers may represent modifications to a mixture through the substitution of a component.

Mixture Name List Box, Name Form

Initially, this list box contains all the mixture names in the database. If a mixture name is selected, NTS-DB searches the database for all tests which used the mixture and displays the results in the Test Name List Box.

If a test is selected from the Test Name List Box, NTS-DB searches the database for all mixtures used on the test and displays the results in the Mixture Name List Box.

Mixture Name List Box, Property/Component Form

Click the Mixture Name List Box to display the mixture names that meet the specified property criterion and/or contain the specified component(s). Once a mixture is selected, NTS-DB searches the database to find all tests which used the mixture. The results of the search are displayed in the Test Name List Box, Property/Component Form.

Notes

Any note recorded for a mixture.

Laboratory notes are presented by clicking the Criteria/Notes button on the Property/Component or Name Forms.

Field notes, specific to a location on a test, are presented on the Field Data Plotting Options Form (when available) after selecting an item from the Select a Location List Box.

NTS-DB Icon

Click the icon to display the About NTS-DB Form.

Available on the Main Form.

Plot Data

Click Plot Data to display a scatter plot of the specified data.

Available on the Laboratory Data and Field Data Forms.

Plot Display

Visible on the Laboratory or Field Data Forms after clicking the Plot Data button.

Hint: Double-click on a data point to see its (x,y) values.

Plotting, Display Commands

These buttons allow the user to alter the Plot Display.

Available on the Laboratory or Field Data Forms after clicking the Plot Data button.

Plotting, Export Commands

These buttons allow the user to save the data values to a file, copy the plot image to the clipboard, copy the data values to the clipboard, and print a hard copy of the plot image.

Available on the Laboratory or Field Data Forms after clicking the Plot Data button.

Print

Click Print to print a hard-copy of the Materials List for a mixture.

Available on the Property/Component and Name Forms after the Materials List button is clicked.

Prior to Shot Day

Click this option to view property data determined Prior To Shot Day.

Available on the Field Data Plotting Options Form.

Property

A material property of a mixture determined from standard test procedures. For example, unconfined compressive strength, density, or static modulus.

Query

The process by which the database is searched, depending on parameters selected by the user.

Query a Property and/or Component

Click Query a Property and/or Component to initiate a Property/Component query.

Available initially on the Main Form or after clicking Cancel.

Query a Mixture Name or Test Name

Click Query a Mixture Name or Test Name to initiate a Name query.

Available initially on the Main Form or after clicking Cancel.

Query Different Property/Comp

Click Query Different Property/Comp to return to the Main Form where the query may be modified.

Available on the Property/Component Form.

Select a Field Test

Select the field test data to view. A single test or all tests using the mixture may be selected. If a single test is selected, the Select a Location List Box is presented.

Available on the Field Data Plotting Options Form.

Select a Location

Select the location on a field test to view. A single location or all locations on a test may be selected.

After a field location is selected, the Date Cast, Temperature Change, and Notes for the location are presented (when available).

Available on the Field Data Plotting Options Form if a single test is selected in the Select a Field Test List Box.

Select a Mixture

A mixture must be selected from the Mixture Name List Box, Property/Component Form. Once selected, NTS-DB searches the database for information about the mixture.

Available on the Property/Component Form.

Select a Mixture and/or Test Name

Each time the mixture name or test name is changed in Mixture Name List Box or Test Name List Box on the Name Form, respectively, NTS-DB updates the other list box to reflect the results of the search.

To initialize the query, the user may select the first item in either of the list boxes "Initialize Lists", or click the Initialize Query Lists button.

Available on the Name Form.

Select Data to View

Choose to view properties determined Prior to Shot Day or on Shot Day.

Available on the Field Data Plotting Options Form.

Select the X-Axis

Choose the parameter to plot along the x-axis. The default is Age. NTS-DB prevents the user from making a selection for which there are no data, i.e., the options are disabled (appearing gray) if there are no data available.

Available on the Laboratory Data and Field Data Forms.

Select the Y-Axis

Choose the parameter to plot along the y-axis. The default is Strength. NTS-DB prevents the user from making a selection for which there are no data, i.e., the options are disabled (appearing gray) if there are no data available.

Available on the Laboratory Data and Field Data Forms.

Set

The condition reached by a mixture when it has lost plasticity to an arbitrary degree, usually measured in terms of resistance to penetration or deformation. Initial set refers to first stiffening; final set refers to attainment of significant rigidity; determined according to ASTM C 463 (concretes) or ASTM C 953 (grouts). Available for laboratory data only.

Presented on the Mixture and Plastic Data Form.

Shot Day

The day a field test was conducted at the Nevada Test Site.

Click this option to view property data determined on Shot Day. The age at which the properties were determined is not available for this option.

Available on the Field Data Plotting Options Form.

Slump

A measure of consistency of a freshly mixed concrete or groutcrete equal to the subsidence measured to the nearest 1/4 in. of the molded specimen immediately after removal of the slump cone; determined according to ASTM C 143. Available for laboratory data only.

Presented on the Mixture and Plastic Data Form.

Static Modulus

The value of Young's modulus of elasticity obtained by arbitrary criteria from measured stress-strain relationships derived from other than dynamic loading; determined according to ASTM C 469.

Strength

Unconfined compressive strength; the measured maximum resistance of a mixture to axial loading, expressed as lb/sq. in.; determined according to ASTM C 39.

Temperature Change

The measured rise in temperature of a mixture; determined according to ASTM D 1064.

Test Name

The name of a test conducted at the Nevada Test Site (NTS).

Test Name List Box, Name Form

Initially, this list box contains all the test names in the database. If a test name is selected, NTS-DB searches the database for all mixtures used on the test and displays the results in the Mixture Name List Box.

If a mixture is selected from the Mixture Name List Box, NTS-DB searches the database for all tests that used the mixture and displays the results in the Test Name List Box.

Test Name List Box, Property/Component Form

Click the Test Name List Box to display the test names that used the mixture selected in the Mixture Name List Box.

Unit Weight

Weight per unit volume of the mixture, expressed as lb/cu ft; determined according to ASTM D 138.

Presented on the Mixture and Plastic Data Form.

Velocity

Sonic (or pulse) velocity; determined according to ASTM C 597.

Water/Cement Ratio

The ratio of the amount of water, exclusive only of that absorbed by the aggregates, to the amount of cement in a mixture.

Presented on the Mixture and Plastic Data Form.

DEPARTMENT OF DEFENSE

DEFENSE INTELLIGENCE AGENCY

ATTN: DT-1
ATTN: DT-18 J HEMPSTEAD
ATTN: PAQUJ KRIESE
ATTN: PQH-48, J DOPERAJSKI
ATTN: R TISDEL
ATTN: TA-5 (R BURGER)
ATTN: TWJ

DEFENSE SPECIAL WEAPONS AGENCY

ATTN: DDJR DR G ULLRICH
ATTN: ESA
ATTN: ESA, K PETERSEN
ATTN: EST/L PRESSLEY
ATTN: EST/R GULLICKSON

3CY ATTN: ISST

ATTN: OPOAA LCDR GOTT
ATTN: OPTN, DR P CASTLEBERRY
ATTN: PM, D LINGER
ATTN: PM, ROHR
ATTN: PMAN/F RENSVOLO
ATTN: PMCVAY, OXFORD
ATTN: PMCO, MAJ D BRUDER
ATTN: PMCO, MAJ P NELSON
ATTN: PMCT, M FLOHR
ATTN: PMP, M SHORE
ATTN: PMPA, DR C GALLOWAY
ATTN: PMPO
ATTN: PMT, D SUNSHINE
ATTN: PMT, K GOERING
ATTN: PMT, P SENSENY
ATTN: WE
ATTN: WE, C MCFARLAND
ATTN: WEL, DR GW ULLRICH
ATTN: WEL/R SELK
ATTN: WEL, D RICE
ATTN: WEL, K KIM
ATTN: WEL, L WITTWER
ATTN: WEL, M GILTRUD
ATTN: WEL, W ZIMMERS
2CY ATTN: WEP, K SCHWARTZ
ATTN: WEP, T KENNEDY
ATTN: XP, LTC KYME

DEFENSE TECHNICAL INFORMATION

2CY ATTN: DTIC/OCF

FC DEFENSE SPECIAL WEAPONS AGENCY

ATTN: FCTN LASHBAUGH
ATTN: FCTN, B HARRIS-WEST
ATTN: MR GARY REYNOLDS
ATTN: TDNV

FC DEFENSE SPECIAL WEAPONS AGENCY

ATTN: FC
ATTN: FCIN, B RISTVET
ATTN: FCST
ATTN: FCST R SMITH
ATTN: FCT-Q E RINEHART
ATTN: FCTI
ATTN: FCTI DR GEOVBELL
ATTN: FCTI AJAY VERMA
ATTN: FCTI GS LU
ATTN: FCTI, E PERALES
ATTN: FCTIH K SHAH
ATTN: FCTIP S THARNSTROM
ATTN: FCTIP, H ROSS
ATTN: FCTM
ATTN: FCTM MR MONTOYA
ATTN: FCTO
ATTN: FCTOE
ATTN: FCTOH
ATTN: FCTOS
ATTN: FCTR JUAN QUINTANA
ATTN: FCTR LT COL COPELAND
ATTN: FCTR MAJ NELSON
ATTN: FCTR, R W SHOUJ
ATTN: FCTT-E, J KING
ATTN: FCTT/MAJ JEFF DURAY
10 CY ATTN: FCTT, DR BALADI
ATTN: FCTT, J HUGHES
ATTN: FCTTD LT COL JAMES
ATTN: FCTTD MAJ P DEREGO
ATTN: FCTTD J THOMPSON
ATTN: FCTTS
ATTN: FCTTS A MARTINEZ
ATTN: FCTTS D SEEMANN
ATTN: FCTTS G GOODFELLOW
ATTN: FCTTS J LEVERETTE
ATTN: FCTTS LTCOL AULETTA
ATTN: FCTTS P RANGLES
ATTN: FCTTS R HENNY
ATTN: FCTTS R MCCRORY
ATTN: FCTTS DR REINKE
ATTN: FCTTS, E MARTINEZ
ATTN: FCTTS E TREMBA

DNA-TR-88-00 (DL CONTINUED)

OFFICE OF SPECIAL TECHNOLOGY
ATTN: J DAVID

DEPARTMENT OF THE ARMY

ADVANCED RESEARCH PROJECT AGENCY
ATTN: DAR (AEROSPACE & STRATEGIC
TECHNOLOGY OFC)
ATTN: DIRECTOR
ATTN: LIBRARY

ARMY RESEARCH LABORATORIES
ATTN: (TECH LIB)
ATTN: AMSRL-OP-SD-TL
ATTN: AMSRL-SL-CN E FIORAVANTE
ATTN: AMSRL-WT-NB-MARY ABE
ATTN: DELHD-TAL, TECH LIB

U S ARMY CORPS OF ENGINEERS
ATTN: V GAUBE

U S ARMY DEPT CH OF STAFF FOR OPS & PLANS
ATTN: DAMO-NCN
ATTN: DAMO-SWN

U S ARMY WAR COLLEGE
ATTN: LIBRARY

U S ARMY DEPUTY COMMANDER MOSTC
ATTN: C3SD-SL-L
ATTN: C3SD-WD

MISSILE DEFENSE & SPACE TECHNOLOGY CTR
ATTN: C3SD-TC-SR

NATICK R & D CENTER
ATTN: B DICRISTAFANO
ATTN: G CALARELLA

U S ARMY NATIONAL RANGE METEOROLOGY
BRANCH
ATTN: STEWS-NRO-DA-S/T C JAMISON

NUCLEAR EFFECTS DIVISION
ATTN: STEWS-NE J LUNDSFORD
ATTN: STEWS-NE J MEASON
ATTN: STEWS-NE-A J OYUMA
ATTN: STEWS-NR-DO C HORN

U S ARMY AVIATION CENTER & FT RUCKER
ATTN: ATZQ-CDC-C TORRENCE

U S ARMY AVIATION SYSTEMS CMD
ATTN: AMCPEO-LHX-TV (D DEIBLER)

U S ARMY CORP OF ENGINEERS
ATTN: CERD-L
ATTN: DAEN-RDL

U S ARMY CORPS OF ENGINEERS
ATTN: CEMRO-ED-SWW GAUBE

U S ARMY ENGINEER DIV HUNTSVILLE
ATTN: HNDED-SY

U S ARMY ENGR WATERWAYS EXPER STATION
2 CY ATTN: B H GREEN

ATTN: B PHILLIPS (CEWES-SD)
ATTN: CEWES-SD-R B ROHANI
ATTN: CEWES-SD-R C WELCH
ATTN: CEWES-SC B NEELEY
ATTN: CEWES-SC, D WALLEY
ATTN: CEWES-SD
ATTN: CEWES-SD O, R MOXLEY

22 CY ATTN: CEWES-SD-R HOWARD WHITE
ATTN: CEWES-SD-R/B ROHORRI
ATTN: CEWES-SE (MR L K DAVIS)
ATTN: CEWES-SS-E, D COLTHARP
ATTN: CEWES-SS-R (W HUFF)
ATTN: CEWES-SS-RE, RANDY HOLMES
ATTN: D FULLER, CEWES-SE-R
ATTN: D RICKMAN, CEWES-SE-R
ATTN: D TILSON
ATTN: E JACKSON, CEWES-SD-R
ATTN: F DALLRIVA, CEWES-SS-R
ATTN: F LEAKE
ATTN: CEWES-SD-R J WINDHAM
ATTN: J ZELASKO, CEWES-SD-R

3 CY ATTN: M HOSSLEY, CEWES-SS-E
ATTN: MARK GREEN
ATTN: MR S SCOTT
ATTN: WESSE-R R WELCH
ATTN: S WOODSON, CEWES-SS-E
ATTN: T SLAWSON
ATTN: TECHNICAL LIBRARY

U S ARMY MISSILE COMMAND
ATTN: AM3M-RD-C8-R DOC CAT

U S ARMY NATIONAL GROUND INTELLIGENCE CENTER

ATTN: C WARD
ATTN: DOCUMENT CONTROL
ATTN: IAFSTC-RMT

U S ARMY NUCLEAR & CHEMICAL AGENCY
ATTN: MONA-AD LIBRARY

U S ARMY RESEARCH DEV & ENGRG CTR
ATTN: STRNG-JE T GARY
ATTN: STRNG-TSC J ROACH

U S ARMY RESEARCH LAB
ATTN: G DUNAWAY (AT-W5)
ATTN: J DAVIS (AT-M)
ATTN: SLCAS-AE-T MR SAUTER
ATTN: SLCAS-A8

U S ARMY RESEARCH LAB
ATTN: AMSRL-OP-CLE, TECH LIBRARY
ATTN: AMSRL-SL-B (OR KLOPCIC)
ATTN: AMSRL-WT-NC (LOTTERO)
ATTN: AMSRL-WR-NC J POIK
ATTN: AMSRL-WT-NC, J SULLIVAN
ATTN: AMSRL-WT-TA(G BULLASH)
2 CY ATTN: SLCBR-DD-T (TECH LIB)
ATTN: SLCBR-SS-T (TECH LIB)
ATTN: SLCBR-TBD, P MULLER

U S ARMY TEST AND EVALUATION COMMAND
ATTN: TECHNICAL LIBRARY B-F

U S ARMY AVIATION AND TROOP COMMAND
ATTN: AMCPEO-LHX-TV (MARK SMITH)

U S ARMY MATERIEL SYS ANALYSIS ACTIVITY
ATTN: AMCSY-CR

U S ARMY TANK AUTOMOTIVE COMMAND
ATTN: A MSTA-JSK (ARMOR ENG BR)

U S ARMY CML & BIOLOGICAL DEFENSE CMD
ATTN: AMSCB-BDUJ CANNALATO

DEPARTMENT OF THE NAVY

DAVID TAYLOR RESEARCH CENTER
ATTN: CODE 1730.2 MR BARTLETT
ATTN: M CRITCHFIELD, CODE 1730.2

NAVAL SURFACE WARFARE CENTER
2 CY ATTN: CODE 050T MICHAEL SWISDAK

NAVAL PLANT REPRESENTATIVE OFFICE
ATTN: R R HESS

NAVAL POSTGRADUATE SCHOOL
ATTN: CODE 52/LIBRARY
ATTN: MS G, X MARUYAMA
ATTN: PROF DONALD L WALTERS
ATTN: SUPERINTENDENT

NAVAL RESEARCH LAB
ATTN: CODE 4040 D BOOK
ATTN: CODE 4005 D BOOK
ATTN: CODE 5227 RESEARCH REPORT
ATTN: JACOB GRUN (CODE 6706)

NAVAL SURFACE WARFARE CENTER
ATTN: CODE H-21
ATTN: TECHNICAL LIBRARY

NAVAL UNDERSEA WARFARE CENTER
ATTN: TECH LIB

NAWC-WD
ATTN: CODE 246 C AUSTIN
ATTN: CODE 343
ATTN: CODE 47332X D MERIGSTAD
ATTN: L JOSEPHSON
ATTN: LIBRARY
ATTN: VX-8 LT OVERSON

WFESC
ATTN: CODE L84, LORY

NUWC, DETACHMENT NLON
ATTN: CODE G281

OFFICE OF CHIEF NAVAL OPERATIONS
ATTN: NUC AFFAIRS & INTL NEGOT BR (N514)

OFFICE OF NAVAL RESEARCH
ATTN: CODE 334

USAAVNC
ATTN: MR TORRANCE

DNA-TR-88-80 (DL CONTINUED)

DEPARTMENT OF THE AIR FORCE

AF CENTER FOR STUDIES & ANALYSIS
ATTN: AFSA/SAI, RM 1D363 THE PENTAGON

AIR UNIVERSITY LIBRARY
ATTN: LDS
ATTN: AUL-LSE

USAF DET 1, 57TH WING
ATTN: CPT VAN DE BERRY
ATTN: LT COL BELL
ATTN: MAJ DOLSON

USAF DET 2 AFOTEC/TF
ATTN: MAJ H WHITING

USAF HQ ACC/DRPW
ATTN: LT COL LEWIS

USAF HQ ACC/WAA
ATTN: MAJ CRONE

USAF/M
ATTN: IN RM 4A832

HQ 487 IG/NOT
ATTN: INT

NATIONAL AIR INTELLIGENCE CENTER
ATTN: SOWDA S SPRING
ATTN: SQDEI MR SONDERGELT

PHILLIPS LABORATORY
ATTN: DR SLIVINSKY PLVT-8
ATTN: JO FRIBBIE, PLWS
ATTN: OLNS
ATTN: PL/SUL

SAN ANTONIO AIR LOGISTICE CTR
ATTN: ALC/S.V MR F CRISTADORO

USAF 8M-ALC/QLA
4 CY ATTN: S SKADOW

US AIR FORCE/ FSTC
ATTN: CAPT WHITWORTH

U S SPACE COMMAND
ATTN: LT COL G E RITCHIE

WRIGHT LABORATORY

ATTN: MAJ FRASIER
ATTN: MAJ GANS WL/MNAMW
ATTN: MNMW, A WEDMORTS
ATTN: MNSA MR PLENGE

WRIGHT LABORATORY

ATTN: WL-FIVC-OL D VICKERS
ATTN: WL-FIVC-OL LIBRARY
ATTN: WL-FIVCS (S STRICKLAND)

WRIGHT LABORTORY

ATTN: WL MNMF, D HAYLES
ATTN: WL MNMF, C TEEL

XORC/BD

ATTN: LTCOL BISHOP
ATTN: MAJ BREWER

USAF 28TH TS/TXWS
ATTN: MAJOR KREGER

USAF 40TH TEST SQUADRON
ATTN: DDOA, T HARTSOE
ATTN: DOUE, R KNOWLES

USAF 47TH WING
ATTN: CPT NEWMAN
ATTN: LTC SMITH

USAF 49TH TESTS/DO
ATTN: LT ELMONT
ATTN: LT SOLLORS
ATTN: LTCOL VILLINES
ATTN: MAJ SAWYER
ATTN: MAJ WHITE
ATTN: 1LT RUSHING

USAF 57TG/TGBD
ATTN: S CARLSON
ATTN: S NETARDUS

DEPARTMENT OF ENERGY

NEVADA OPERATIONS OFFICE
2 CY ATTN: D N BURGESS
2 CY ATTN: G L WINTERGEST

DEPARTMENT OF ENERGY
ATTN: M DE.MY

WEAPONS PRODUCTION DIVISION
ATTN: OMA/VP-225

LAWRENCE LIVERMORE NATIONAL LAB

ATTN: ALLEN KUHLE
ATTN: C E ROSENKOLDE
ATTN: DAVID STANFEL
ATTN: F HELUZE
ATTN: G MARA
ATTN: J BELL (L-316)
ATTN: L-200/J RAMBO
ATTN: L-200/J WHITE
ATTN: L-200/W C MOSS
ATTN: L-200, D B CLARKE
ATTN: L-41 J MORGAN
ATTN: L-43 R BENJAMIN
ATTN: L-81 R PERRETT
ATTN: L-84/G POMYKAL
ATTN: L-86 H CABAYAN
ATTN: M TOBIN, L-459
ATTN: REPORTS LIBRARY
ATTN: TECH LIBRARY

LOS ALAMOS NATIONAL LABORATORY

ATTN: D HOLDEN
ATTN: D218 MS M HENDERSON
ATTN: INC-7, MS J514 A MASON
ATTN: M BUCHWALD MS D438
ATTN: MS C335 TOM WEAVER
ATTN: MS D408/T MCKOWN
ATTN: MS F665, R SWIFT
ATTN: MS J514/A S MASON
ATTN: MS J970/J FRITZ
ATTN: MS J978/C MORRIS

2 CY ATTN: MS P364 REPORT LIBRARY

ATTN: MS-8221/J N JOHNSON
ATTN: MS-P470, R KRBY
ATTN: MS218 P WHALEN
ATTN: R HAGAN, MS-D409
ATTN: R W WHITAKER
ATTN: REPORT LIBRARY
ATTN: S S HECKER
ATTN: SUNG HAN
ATTN: WX-11, R SHARP

SANDIA NATIONAL LABORATORIES

ATTN: B ZAKMS 0755
ATTN: BRAD PARKS
ATTN: D A LANDAMS 0072

ATTN: D BEUTLERMS 1179
ATTN: D HIGGENSAMS 0047
ATTN: D VEHAR
ATTN: DIV 9322, D GARBINMS 1100
ATTN: DR R SHAGAM
ATTN: G LOCKWOODMS 1159
ATTN: J M MCGLAUNMS 0019
ATTN: L HILLMS 1345
ATTN: M FORRESTALMS 0312
ATTN: MIKE FURNISHMS 0621
ATTN: MR BONAGUIDMS 1308
ATTN: ORG 9311/R E PEPPINGMS 1159
ATTN: R LUNGREN, MS 0312
ATTN: R SPEIMANMS 1194
ATTN: T K BERGSTRESSERMS 1180
2 CY ATTN: TECH LIB
ATTN: TECH LIBMS 0800
ATTN: W BALLARDMS 1179

OTHER GOVERNMENT

BUREAU OF ALCOHOL, TOBACCO & FIREARMS

ATTN: D NEIMAN
3 CY ATTN: D SHATZER
ATTN: P HORBERT

CENTRAL INTELLIGENCE AGENCY

ATTN: OSWR/NEED 5509 NHB

DEPARTMENT OF THE INTERIOR

ATTN: D RODDY

FEDERAL EMERGENCY MANAGEMENT AGENCY

ATTN: OFC OF CIVIL DEFENSE
ATTN: OFC OF RSCH

NATIONAL INSTITUTE OF STANDARDS & TECHNOLOGY

ATTN: R LEVINE

U S GEOLOGICAL SURVEY

ATTN: DR RODDY

DEPARTMENT OF DEFENSE CONTRACTORS

APPLIED RESEARCH ASSOCIATES

ATTN: H COOPER

APPLIED RESEARCH ASSOCIATES, INC.

ATTN: C J HIGGINS

ATTN: D COLE
ATTN: K BELL
ATTN: M PLAMONDON
ATTN: N BAUM
ATTN: P ROUPAS

UNIVERSITY OF ARIZONA
ATTN: LIBRARY

ENSCO INC
ATTN: COLLIN SHELLUM
ATTN: DOGUM BOUMGARDT
ATTN: P FISHER
ATTN: R HAMRICK

KAMAN SCIENCES CORP
ATTN: DASIAC B BOUGARD

KAMAN SCIENCES CORP
2 CY ATTN: DASIAC

LOCKHEED MARTIN CORPORATION
ATTN: B MEENDERING

LOGICON R AND D ASSOCIATES
ATTN: B GOULD
ATTN: R GILBERT

LOGICON R AND D ASSOCIATES
ATTN: E FURBEE

LOGICON R AND D ASSOCIATES
ATTN: G GANONG
ATTN: J RENICK

MASSACHUSETTS INSTITUTE OF TECHNOLOGY
ATTN: LIBRARY

MAXWELL TECHNOLOGIES
ATTN: JOHN RAUCH

PHYSICS INTERNATIONAL CO.
ATTN: R L SCHNEIDER
ATTN: S L WONG

SCIENCE APPLICATIONS INTERNATIONAL CORP
ATTN: C HSIAO
ATTN: L SCOTT

SCIENCE APPLICATIONS INTERNATIONAL CORP

ATTN: E E O'DONNELL
ATTN: R MILLER

SUMNER ASSOCIATES
ATTN: A S MASON

SVERDRUP TECHNOLOGY INC
ATTN: M BABINEAU
ATTN: V KENYON

TECH REPS, INC.
ATTN: F MCMULLAN
ATTN: J LUND

TITAN CORPORATION
ATTN: C SCHEFFIELD
ATTN: J ROCCO
ATTN: J THOMSEN
ATTN: S BABCOCK

DIRECTORY OF OTHER (LIBRARY AND
UNIVERSITIES)

ALABAMA A&M UNIVERSITY
ATTN: LIBRARY

ALABAMA, UNIVERSITY OF
ATTN: DIRECTOR OF LIBRARIES

ALASKA, UNIVERSITY OF
ATTN: DIRECTOR OF LIBRARIES
ATTN: LIBRARY, 202 BUTROVICH BLDG

ALASKA, UNIVERSITY OF
ATTN: GOVERNMENT PUBLICATION
LIBRARIAN

ALCORN STATE UNIVERSITY
ATTN: LIBRARY

AMERICAN INDIAN HIGHER EDUCATION
ATTN: LIBRARY

ARIZONA STATE UNIVERSITY
ATTN: LIBRARY

ARIZONA UNIVERSITY
ATTN: LIBRARIAN

ARIZONA, UNIVERSITY OF

ATTN: GOV DOC DEPT

ARKANSAS STATE UNIVERSITY
ATTN: LIBRARY

ARKANSAS, UNIVERSITY OF
ATTN: GOVERNMENT DOCUMENTS DIV
ATTN: LIBRARY, 425 ADMIN BLDG

AUBURN UNIV AT MONTGOMERY LIBRARY
ATTN: LIBRARIAN

AUBURN UNIVERSITY
ATTN: M ROSE

AUBURN UNIVERSITY
ATTN: LIBRARY

BAY MILL COMMUNITY COLLEGE
ATTN: LIBRARY

BLACKFECT COMMUNITY COLLEGE
ATTN: LIBRARY

BOSTON UNIVERSITY
ATTN: MICHAEL MENDILLO

BOWDOIN COLLEGE
ATTN: LIBRARIAN

BOWLING GREEN STATE UNIV
ATTN: LIB GOVT DOCS SERVICES

BRIGHAM YOUNG UNIVERSITY
ATTN: DOCUMENTS COLLECTION

BROWN UNIVERSITY
ATTN: LIBRARIAN

BUCKNELL UNIVERSITY
ATTN: O ANDERSON
ATTN: REFERENCE DEPT

CALIFORNIA AT FRESNO STATE UNIV LIB
ATTN: LIBRARY

CALIFORNIA AT LOS ANGELES, UNIVERSITY OF
ATTN: J MACKENZIE
ATTN: T FARLEY

CALIFORNIA AT SAN DIEGO UNIVERSITY
ATTN: DOCUMENTS DEPARTMENT

CALIFORNIA INSTITUTE OF TECHNOLOGY
ATTN: E LEWIS
ATTN: R CHRISTY

CALIFORNIA, UNIVERSITY OF
ATTN: L BADASH/DEPT OF HISTORY

CASE WESTERN RESERVE UNIVERSITY
ATTN: LIBRARY

CENTRAL FLORIDA UNIV OF
ATTN: LIBRARY DOCS DEPT

CENTRAL WYOMING COLLEGE LIBRARY
ATTN: LIBRARIAN

CHICAGO, UNIVERSITY OF
ATTN: P MEIER

CLEMSON UNIVERSITY
ATTN: DIRECTOR OF LIBRARIES

COLORADO STATE UNIV LIBS
ATTN: LIBRARY

COLORADO, UNIVERSITY LIBRARIES
ATTN: DIRECTOR OF LIBRARIES
ATTN: J BIRKS
ATTN: R SCHNELL CAMPUS BOX 440

CONNECTICUT AG EXPERIMENT STATION
ATTN: LIBRARY

CONNECTICUT UNIVERSITY OF
ATTN: GOVERNMENT OF CONNECTICUT

CORNELL UNIVERSITY
ATTN: W FEDERER

CORNELL UNIVERSITY
ATTN: LIBRARY

CORNELL UNIVERSITY
ATTN: LIBRARIAN

D-Q UNIVERSITY (LOWER DIVISION)
ATTN: LIBRARY

DARTMOUTH COLLEGE
ATTN: LIBRARIAN

DAYTON, UNIVERSITY OF
ATTN: LIBRARIAN

DELAWARE STATE UNIVERSITY
ATTN: LIBRARY

DULL KNIFE COMMUNITY COLLEGE
ATTN: LIBRARY

FLORIDA A & M UNIV
ATTN: LIBRARY RM 400, LEE HALL

FLORIDA INSTITUTE OF TECH LIB
ATTN: GOVT DOCUMENTS DEPT

FLORIDA STATE LIBRARY
ATTN: DOCUMENTS STROZIER R-113

FLORIDA STATE UNIVERSITY
ATTN: DOCUMENTS DEPARTMENT

FORT VALLEY STATE COLLEGE
ATTN: LIBRARY

FT BELKNAP COMMUNITY COLLEGE
ATTN: LIBRARY

FT BETHOLD COMMUNITY COLLEGE
ATTN: LIBRARY

FT PECK COMMUNITY COLLEGE
ATTN: LIBRARY

GEORGE MASON UNIVERSITY
ATTN: R EHRUCH

GEORGE WASHINGTON UNIVERSITY
ATTN: R GOULARD

GEORGETOWN UNIV LIBRARY
ATTN: GOVT DOCS ROOM

GEORGIA INST OF TECH
ATTN: E PATTERSON
ATTN: LIBRARIAN

GEORGIA TECHNOLOGICAL INSTITUTE

ATTN: DR JOHN ENDICOTT

GEORGIA, UNIVERSITY OF
ATTN: LIBRARY
ATTN: LUSTRAT HOUSE/LIBRARY

HARVARD COLLEGE LIBRARY
ATTN: DIRECTOR OF LIBRARIES
ATTN: W PRESS

HARVARD UNIVERSITY
ATTN: G CARRIER
ATTN: LIBRARY
ATTN: M MCELROY
ATTN: SECURITY OFFICER

HASKELL INDIAN NATIONS UNIVERSITY
ATTN: LIBRARY

IDAHO STATE UNIVERSITY
ATTN: DOCUMENTS DEPARTMENT

IDAHO, UNIVERSITY OF
ATTN: LIBRARY

ILLINOIS STATE LIBRARY (REGIONAL)
ATTN: GOVERNMENT DOCUMENTS
BRANCH

INDIANA STATE LIBRARY (REGIONAL)
ATTN: SERIAL SECTION

INDIANA STATE UNIVERSITY
ATTN: DOCUMENTS LIBRARIES

INSTITUTE OF AMERICAN INDIAN AND ALASKA
NATIVE CULTURE AND AREA DEVELOPMENT
ATTN: LIBRARY

IOWA STATE UNIVERSITY LIBRARY
ATTN: GOVERNMENT DOCUMENT
DEPARTMENT

IOWA UNIVERSITY LIBRARY
ATTN: GOVERNMENT DOCUMENTS DEPT

JOHN HOPKINS UNIVERSITY
ATTN: DOCUMENTS LIBRARY

JOHN HOPKINS UNIVERSITY ATTN: A KIMBALL	ATTN: LIBRARIAN
KANSAS STATE UNIVERSITY LIBRARY ATTN: DOCUMENTS DEPARTMENT	MICHIGAN UNIVERSITY OF ATTN: ACQ SEC DOCUMENTS UNIT
KANSAS, UNIVERSITY OF ATTN: DIRECTOR OF LIBRARIES	MICHIGAN, UNIVERSITY OF ATTN: R CORNELL
KENTUCKY DEPT OF LIBRARY & ARCHIVES ATTN: DOCUMENTS SECTION	MINNESOTA, UNIVERSITY OF ATTN: J BEARMAN ATTN: L SCHUKMAN
KENTUCKY STATE UNIVERSITY ATTN: LIBRARY	MISSISSIPPI STATE UNIVERSITY ATTN: LIBRARIAN
KENTUCKY, UNIVERSITY OF ATTN: DIRECTOR OF LIBRARIES	MISSISSIPPI STATE UNIVERSITY ATTN: LIBRARY
LAC COURIE ORELLES OJIBWA ATTN: LIBRARY	MISSISSIPPI, UNIVERSITY OF ATTN: DIRECTOR OF LIBRARIES
LANGSTON UNIVERSITY ATTN: LIBRARY	MISSOURI UNIV AT KANSAS CITY GEN ATTN: LIBRARIAN
LINCOLN UNIVERSITY ATTN: LIBRARY	MISSOURI, UNIVERSITY LIBRARY ATTN: GOVERNMENT DOCUMENTS
LITTLE BIG HORN COLLEGE ATTN: LIBRARY	MONTANA STATE LIBRARY ATTN: LIBRARIAN
LITTLE HOOP COMMUNITY COLLEGE ATTN: LIBRARY	MONTANA STATE UNIVERSITY LIB ATTN: LIBRARIAN
LOUISIANA STATE UNIVERSITY SYSTEMS ATTN: LIBRARY	MONTANA STATE UNIVERSITY LIB ATTN: LIBRARY
LOUISIANA TECH UNIVERSITY ATTN: GOVERNMENT DOCUMENTS DEPT	NATRONA COUNTY PUBLIC LIBRARY ATTN: LIBRARIAN
MASSACHUSETTS UNIV OF ATTN: GOVERNMENT DOCS COLLEGE	NAVAJO COMMUNITY COLLEGE ATTN: LIBRARY
MEMPHIS STATE UNIV LIBRARY ATTN: LIBRARIAN	NEBRASKA INDIAN COMMUNITY COLLEGE ATTN: LIBRARY
NEANE LIBRARY UNIVERSITY OF ATTN: C CONVEY ATTN: GOVERNMENT PUBLICATIONS	NEBRASKA OMAHA UNIV OF ATTN: LIBRARIAN
MICHIGAN STATE UNIVERSITY LIBRARY	NEVADA LIBRARY UNIV OF ATTN: LIBRARY

NEVADA, UNIVERSITY AT LAS VEGAS
ATTN: DIRECTOR OF LIBRARIES

NEW MEXICO STATE LIBRARY
ATTN: LIBRARIAN

NEW MEXICO STATE UNIVERSITY
ATTN: LIBRARY

NEW MEXICO, UNIV OF SCHOOL OF MEDICINE
ATTN: C KEY
ATTN: R ANDERSON

NEW YORK STATE UNIV AT STONY BROOK
ATTN: MAIN LIB DOCUMENTS SECTION

NEW YORK STATE UNIV COL AT CORTLAND
ATTN: LIBRARIAN

NEW YORK STATE UNIVERSITY
ATTN: DOCUMENTS CENTER

NEW YORK UNIVERSITY DEPARTMENT OF
ENVIRONMENTAL MEDICINE
ATTN: A UPTON
ATTN: LIBRARY

NORTH CAROLINA A&T STATE UNIVERSITY
ATTN: LIBRARY

NORTH CAROLINA STATE UNIVERSITY
ATTN: LIBRARIAN

NORTH CAROLINA STATE UNIVERSITY
ATTN: LIBRARY

NORTH CAROLINA, UNIVERSITY OF
ATTN: LIBRARY FOR DEAN

NORTH DAKOTA STATE UNIVERSITY
ATTN: LIBRARY

NORTH DAKOTA UNIVERSITY OF
ATTN: LIBRARIAN

NORTHWEST INDIAN COLLEGE
ATTN: LIBRARY

NORTHWESTERN UNIVERSITY LIB

ATTN: GOVT PUBLICATIONS DEPT

NOTRE DAME, UNIVERSITY OF
ATTN: DOCUMENT CENTER

OGLALA LAKOTA COLLEGE
ATTN: LIBRARY

OHIO STATE LIBRARY
ATTN: LIBRARIAN

OHIO STATE UNIVERSITY
ATTN: LIBRARIES DOCUMENTS DIVISION

OHIO STATE UNIVERSITY
ATTN: LIBRARY

OKLAHOMA STATE UNIV LIBRARY
ATTN: DOCUMENTS DEPT

OKLAHOMA STATE UNIV LIBRARY
ATTN: LIBRARY

OKLAHOMA, UNIVERSITY OF SCHOOL OF
PUBLIC HEALTH
ATTN: P ANDERSON

OREGON STATE LIBRARY
ATTN: LIBRARIAN

OREGON STATE UNIVERSITY
ATTN: LIBRARY

OREGON, UNIVERSITY OF DIVISION OF
IMMUNOLOGY, ALLERGY & RHEUMATOLOGY
ATTN: S PIROFSKY

PENNSYLVANIA STATE LIBRARY
ATTN: GOVERNMENT PUBLICATIONS
SECTION

PENNSYLVANIA STATE UNIVERSITY
ATTN: LIBRARY

PENNSYLVANIA, UNIVERSITY OF SCHOOL OF
MEDICINE
ATTN: P NOWELL

PENNSYLVANIA, UNIVERSITY OF
ATTN: DIRECTOR OF LIBRARIES

PITTSBURGH, UNIV OF ATTN: E MADFORD ATTN: LIBRARY	SOUTH DAKOTA STATE UNIVERSITY ATTN: LIBRARY
PRAIRIE VIEW A&M UNIVERSITY ATTN: LIBRARY	SOUTH DAKOTA, UNIVERSITY OF ATTN: DOCUMENTS LIBRARIAN
PRINCETON UNIVERSITY ATTN: DR FRANK VON HIPPLE	SOUTHEAST MISSOURI STATE UNIVERSITY ATTN: KENT LIBRARY
PURDUE UNIVERSITY LIBRARY ATTN: LIBRARIAN	SOUTHERN CALIFORNIA UNIV LIBRARY ATTN: DOCUMENTS DEPARTMENT
RHODE ISLAND, UNIVERSITY OF ATTN: DIRECTOR OF LIBRARIES	SOUTHERN CALIFORNIA, UNIV OF ATTN: J BIRREN
LIBRARY OF SCIENCE & MEDICINE RUTGERS UNIVERSITY ATTN: GOVERNMENT DOCUMENTS DEPT.	SOUTHERN ILLINOIS UNIVERSITY ATTN: LOVEJOY MEM LIBRARY
RUTGERS UNIVERSITY ATTN: LIBRARIAN	SOUTHERN METHODIST UNIVERSITY ATTN: B STUMP ATTN: FONDREN LIBRARY
SHALSH KOOTENAI COLLEGE ATTN: LIBRARY	SOUTHERN MISSISSIPPI UNIV OF ATTN: LIBRARY
SAMFORD UNIVERSITY ATTN: LIBRARY	SOUTHERN UNIVERSITY SYSTEM ATTN: LIBRARY
SAN DIEGO STATE UNIV LIBRARY ATTN: GOVT PUBS DEPT	SOUTHWEST INDIAN POLYTECHNIC INSTITUTE ATTN: LIBRARY
SAN JOSE STATE COLLEGE LIBRARY ATTN: DOCUMENTS DEPT	STANDING ROCK COLLEGE ATTN: LIBRARY
SANTE GLESKA UNIVERSITY ATTN: LIBRARY	STANFORD UNIVERSITY ATTN: L MUSEZ
SHASTON WASHINGTON COMMUNITY COLLEGE ATTN: LIBRARY	STANFORD UNIVERSITY LIBRARY ATTN: GOVT DOCUMENTS DEPT
SOUTH CAROLINA STATE LIBRARY ATTN: LIBRARY	STONE CHILD COLLEGE ATTN: LIBRARY
SOUTH CAROLINA STATE UNIVERSITY ATTN: LIBRARY	SARACUSE UNIVERSITY LIBRARY ATTN: DOCUMENTS DIVISION
SOUTH CAROLINA, UNIVERSITY OF ATTN: GOVERNMENTS DOCUMENTS	TEMPLE UNIVERSITY ATTN: DOCUMENTS DEPT
	TENNESSEE STATE UNIVERSITY

ATTN: LIBRARY	UNIVERSITY OF DELAWARE LIBRARY ATTN: LIBRARIAN
TENNESSEE, UNIVERSITY OF ATTN: K FOX	UNIVERSITY OF FLORIDA ATTN: LIBRARY
TEXAS A & M UNIVERSITY LIBRARY ATTN: LIBRARY	UNIVERSITY OF HAWAII ATTN: LIBRARY
TEXAS, AT AUSTIN, UNIV OF ATTN: H SUTTON	UNIVERSITY OF ILLINOIS ATTN: DOCUMENTS LIBRARY
TEXAS TECH UNIVERSITY LIBRARY ATTN: GOVERNMENT DOCUMENTS DEPT	UNIVERSITY OF ILLINOIS ATTN: LIBRARY
TEXAS, UNIVERSITY OF ATTN: C S COOK	UNIVERSITY OF MAINE ATTN: LIBRARY
TULANE UNIVERSITY ATTN: DOCUMENTS DEPT	UNIVERSITY OF MARYLAND ATTN: GEORGE QUESTER
TURTLE MOUNTAIN COMMUNITY COLLEGE ATTN: LIBRARY	UNIVERSITY OF MARYLAND EASTERN SHORE ATTN: LIBRARY
TUSKEGEE UNIVERSITY ATTN: LIBRARY	UNIVERSITY OF MASSACHUSETTS ATTN: LIBRARY
UCLA RESEARCH LIBRARY ATTN: PUBLIC AFFAIRS SERVICE/US DOC3	UNIVERSITY OF MINNESOTA ATTN: LIBRARY
UNITED TRIES TECHNICAL COLLEGE ATTN: LIBRARY	UNIVERSITY OF MISSOURI SYSTEMS ATTN: LIBRARY
UNIVERSITY OF ARIZONA ATTN: HYATT GIBBS	UNIVERSITY OF NEBRASKA ATTN: LIBRARY
UNIVERSITY OF ARKANSAS PINE BLUFF ATTN: LIBRARY	UNIVERSITY OF NEW HAMSHIRE ATTN: LIBRARY
UNIVERSITY OF CALIFORNIA SYSTEM ATTN: LIBRARY	UNIVERSITY OF OREGON LIBRARY ATTN: DOCUMENTS SECTION
UNIVERSITY OF CALIFORNIA, SAN DIEGO ATTN: DR HERBERT YORK, ATTN: SING LEE 0407	UNIVERSITY OF PUERTO RICO ATTN: LIBRARY
UNIVERSITY OF CONNECTICUT ATTN: LIBRARY	UNIVERSITY OF RHODE ISLAND ATTN: LIBRARY
UNIVERSITY OF DELAWARE ATTN: LIBRARY	UNIVERSITY OF SANTA CLARA ATTN: DOCUMENTS DIV - ORRACRE LIB

UNIVERSITY OF SOUTH CAROLINA
ATTN: T S GUDARJIAN

UNIVERSITY OF SOUTH FLORIDA
ATTN: S YING

UNIV OF SOUTHERN CALIFORNIA
ATTN: ARMOND TANGUAY

UNIVERSITY OF SOUTHERN CALIFORNIA SCHOOL
OF INTERNATIONAL RELATIONS
ATTN: RONALD STCAL

UNIVERSITY OF TENNESSEE
ATTN: LIBRARY

UNIVERSITY OF THE DISTRICT OF COLUMBIA
ATTN: LIBRARY, RM 301

UNIVERSITY OF THE VIRGIN ISLANDS
ATTN: LIBRARY

UNIVERSITY OF WASHINGTON
ATTN: G LEOVY
ATTN: L RAOKE
ATTN: P HOBBS

UNIVERSITY OF WISCONSIN-MADISON
ATTN: KURT F WENDT

UNIVERSITY OF WISCONSIN-MADISON
ATTN: LIBRARY

UNIVERSITY OF WISCONSIN-OSHKOSH
ATTN: DOCUMENTS DEPT

UNIVERSITY OF WYOMING
ATTN: LIBRARY

UTAH STATE UNIVERSITY
ATTN: LIBRARY

UTAH, UNIVERSITY OF
ATTN: SPECIAL COLLECTIONS

VANDERBILT UNIVERSITY
ATTN: R QUINN

VIRGINIA MILITARY INSTITUTE
ATTN: DOCUMENTS DEPARTMENT

VIRGINIA POLYTECHNIC INSTITUTE
ATTN: DOCUMENTS DEPARTMENT

VIRGINIA STATE UNIVERSITY
ATTN: LIBRARY

VIRGINIA, UNIVERSITY OF
ATTN: PUBLIC DOCUMENTS

WASHINGTON STATE LIBRARY
ATTN: DOCUMENTS SECTION

WASHINGTON STATE UNIV
ATTN: 302 DOCUMENTS SECTION

WASHINGTON STATE UNIVERSITY
ATTN: MICHAEL K.W. WONG
ATTN: Y M GUPTA

WASHINGTON STATE UNIVERSITY
ATTN: LIBRARY

WASHINGTON UNIVERSITY OF
ATTN: DOCUMENTS DIVISION

WASHINGTON, UNIVERSITY OF SCHOOL OF
PUBLIC HEALTH
ATTN: D THOMSPCN

WILLIAM AND MARY COLLEGE
ATTN: DOCS DEPT

WISCONSIN UNIVERSITY OF GREEN BAY
LIBRARY
ATTN: GOV PUBS DEPT

WISCONSIN, UNIVERSITY OF
ATTN: J CROW

YALE UNIVERSITY
ATTN: COUNCIL OF ENGINEERING
ATTN: G SCHULTZ
ATTN: V HUGHES
ATTN: W RAITH

SUPPLEMENTARY

INFORMATION

ERRATA

for

DSWA-TR-96-99

UNCLASSIFIED

Users Manual for Nevada Test Site Database (NTS-DB) Software

This report was published using DNA-TR-96-99 on the front cover and block 10 of the SF 298.
It should read DSWA-TR-96-99.

Please insert the corrections using the sticky back provided.

DSWA-TR-96-99

DSWA-TR-96-99

A286919

ERRATA

for

DSWA-TR-96-99

UNCLASSIFIED

Users Manual for Nevada Test Site Database (NTS-DB) Software

This report was published using DNA-TR-96-99 on the front cover and block 10 of the SF 298.

It should read DSWA-TR-96-99.

Please insert the corrections using the sticky back provided.

DSWA-TR-96-99

DSWA-TR-96-99